

Tri-Tech ModMap rev2 08/19/2016

Board ID	MOD Nam	Address	s/Master Description	Size	Word Size	4-20ma Description	Data Interpretation
ID 1	400000	0	CommFail	1 int (2 bytes)	1		
	400001	1	SetupChanged	1 int (2 bytes)	1	SetupChanged	SetupChanged
	400002	2	BoardType	1 int (2 bytes)	1	BoardType	System – DO NOT USE
	400003	3	Horn	1 int (2 bytes)	1	Horn	
	400004	4	ETextState	1 int (2 bytes)	1	EtextState	Board Types
	400005	5	MasterAlarm	1 int (2 bytes)	1	MasterAlarm	0=None
	400006	6	GasAlarm[0]	1 int (2 bytes)	1		1=Gas
	400007	7	GasAlarm[1]	1 int (2 bytes)	1		2=Master
	400008	8	GasAlarm[2]	1 int (2 bytes)	1		3=Gas Sensor Master
	400009	9	GasAlarm[3]	1 int (2 bytes)	1		4=4-20ma
	400010	10	Pressure[0]	1 int (2 bytes)	1	Current Value	
	400011	11	Pressure[1]	1 int (2 bytes)	1	Current Value	Horn
	400012	12	Pressure[2]	1 int (2 bytes)	1	Current Value	0=Horn Off
	400013	13	Pressure[3]	1 int (2 bytes)	1	Current Value	Not 0=Horn On
	400014	14	AlarmRepeatDelay	1 int (2 bytes)	1	AlarmRepeatDelay	
	400015	15	LogicType	1 int (2 bytes)	1	LogicType	EtextState
	400016	16	Language	1 int (2 bytes)	1	Language	0=Showing Normal
	400017	17	GasType[0]	1 int (2 bytes)	1		Not 0=Showing Etext
	400018	18	GasType[1]	1 int (2 bytes)	1		
	400019	19	GasType[2]	1 int (2 bytes)	1		MasterAlarm-Master Board Type
	400020	20	GasType[3]	1 int (2 bytes)	1		0=No Alarm
	400021	21	Units[0]	1 int (2 bytes)	1		Bit 0=1:Alarm 1
	400022	22	Units[1]	1 int (2 bytes)	1		Bit 1=1:Alarm 2
	400023	23	Units[2]	1 int (2 bytes)	1		Bit 2=1:Alarm 3
	400024	24	Units[3]	1 int (2 bytes)	1		Bit 3=1:Alarm 4
	400025	25	HiLimit[0]	1 int (2 bytes)	1	HiAlarm LS Word	Bit 4=1:Alarm 5
	400026	26	HiLimit[1]	1 int (2 bytes)	1	HiAlarm MS Word	Bit 5=1:Alarm 6
	400027	27	HiLimit[2]	1 int (2 bytes)	1	Scale 20ma LS Word	Bit 6=1:Alarm 7
	400028	28	HiLimit[3]	1 int (2 bytes)	1	Scale 20ma MS Word	Bit 7=1:Alarm 8
	400029	29	LoLimit[0]	1 int (2 bytes)	1	LoAlarm LS Word	
	400030	30	LoLimit[1]	1 int (2 bytes)	1	LoAlarm MS Word	MasterAlarm-Gas Board Type
	400031	31	LoLimit[2]	1 int (2 bytes)	1	Scale 4ma LS Word	0=No Alarm
	400032	32	LoLimit[3]	1 int (2 bytes)	1	Scale 4ma MS Word	1=Memory Error
	400033	33	PressureOffset[0]	1 int (2 bytes)	1		2=Broken Sensor Wire
	400034	34	PressureOffset[1]	1 int (2 bytes)	1		3=Sensor Comm Failure
	400035	35	PressureOffset[2]	1 int (2 bytes)	1		4=Sensor Noise Error
	400036	36	PressureOffset[3]	1 int (2 bytes)	1		5=Sensor Type Mismatch
	400037	37	DisplayedText[0]	ints (72 chars + 1 int)	37	Displayed Text	6=Low Alarm

	400074	74	DisplayedText[1] ints (72 chars + 1 int)	37	Name Text	7=High Alarm
	400111	111	DisplayedText[2] ints (72 chars + 1 int)	37	Units Text	
	400148	148	DisplayedText[3] ints (72 chars + 1 int)	37		GasAlarm-Gas Sensor Master
	400185	185	DisplayedText[4] ints (72 chars + 1 int)	37		0=No Alarm
	400222	222	DisplayedText[5] ints (72 chars + 1 int)	37		1=Memory Error
	400259	259	DisplayedText[6] ints (72 chars + 1 int)	37		2=Broken Sensor Wire
	400296	296	DisplayedText[7] ints (72 chars + 1 int)	37	317	3=Sensor Comm Failure
ID 2	400613	613	CommFail	1 int (2 bytes)	1	4=Sensor Noise Error
	400614	614	SetupChanged	1 int (2 bytes)	1	5=Sensor Type Mismatch
	400615	615	BoardType	1 int (2 bytes)	1	6=Low Alarm
	400616	616	Horn	1 int (2 bytes)	1	7=High Alarm
	400617	617	ETextState	1 int (2 bytes)	1	AlarmRepeatDelay
	400618	618	MasterAlarm	1 int (2 bytes)	1	Value=Number of Minutes
	400619	619	GasAlarm[0]	1 int (2 bytes)	1	
	400620	620	GasAlarm[1]	1 int (2 bytes)	1	LogicType
	400621	621	GasAlarm[2]	1 int (2 bytes)	1	0=Non-Latching
	400622	622	GasAlarm[3]	1 int (2 bytes)	1	1=Latching
	400623	623	Pressure[0]	1 int (2 bytes)	1	
	400624	624	Pressure[1]	1 int (2 bytes)	1	Language
	400625	625	Pressure[2]	1 int (2 bytes)	1	0=English/NFPA
	400626	626	Pressure[3]	1 int (2 bytes)	1	1=French/ISO
	400627	627	AlarmRepeatDelay	1 int (2 bytes)	1	2=Spanish/NFPA
	400628	628	LogicType	1 int (2 bytes)	1	3=Spanish/ISO
	400629	629	Language	1 int (2 bytes)	1	
	400630	630	GasType[0]	1 int (2 bytes)	1	GasType
	400631	631	GasType[1]	1 int (2 bytes)	1	0=Nitrogen
	400632	632	GasType[2]	1 int (2 bytes)	1	1=Oxygen
	400633	633	GasType[3]	1 int (2 bytes)	1	2=Nitrous Oxide
	400634	634	Units[0]	1 int (2 bytes)	1	3=Carbon Dioxide
	400635	635	Units[1]	1 int (2 bytes)	1	4=Vacuum
	400636	636	Units[2]	1 int (2 bytes)	1	5=Evacuation
	400637	637	Units[3]	1 int (2 bytes)	1	6=Medical Air
	400638	638	HiLimit[0]	1 int (2 bytes)	1	7=Helium
	400639	639	HiLimit[1]	1 int (2 bytes)	1	8=Hyperbaric Oxygen
	400640	640	HiLimit[2]	1 int (2 bytes)	1	9=High Pressure Carbon Dioxide
	400641	641	HiLimit[3]	1 int (2 bytes)	1	10=Gas Mixture
	400642	642	LoLimit[0]	1 int (2 bytes)	1	11=High Pressure Utility Air
	400643	643	LoLimit[1]	1 int (2 bytes)	1	12=High Pressure Gas Mixture
	400644	644	LoLimit[2]	1 int (2 bytes)	1	13=Tri Gas

400645	645	LoLimit[3]	1 int (2 bytes)	1	
400646	646	PressureOffset[0]	1 int (2 bytes)	1	Units
400647	647	PressureOffset[1]	1 int (2 bytes)	1	0=PSI
400648	648	PressureOffset[2]	1 int (2 bytes)	1	1=Bar
400649	649	PressureOffset[3]	1 int (2 bytes)	1	2=KPA
400650	650	DisplayedText[0]	ints (72 chars + 1 int)	37	3=InchHG
400687	687	DisplayedText[1]	ints (72 chars + 1 int)	37	4=MMHG
400724	724	DisplayedText[2]	ints (72 chars + 1 int)	37	
400761	761	DisplayedText[3]	ints (72 chars + 1 int)	37	
400798	798	DisplayedText[4]	ints (72 chars + 1 int)	37	
400835	835	DisplayedText[5]	ints (72 chars + 1 int)	37	
400872	872	DisplayedText[6]	ints (72 chars + 1 int)	37	
400909	909	DisplayedText[7]	ints (72 chars + 1 int)	37	

ID 3	401226	1226	CommFail	1 int (2 bytes)	1
	401227	1227	SetupChanged	1 int (2 bytes)	1
	401228	1228	BoardType	1 int (2 bytes)	1
	401229	1229	Horn	1 int (2 bytes)	1
	401230	1230	ETextState	1 int (2 bytes)	1
	401231	1231	MasterAlarm	1 int (2 bytes)	1
	401232	1232	GasAlarm[0]	1 int (2 bytes)	1
	401233	1233	GasAlarm[1]	1 int (2 bytes)	1
	401234	1234	GasAlarm[2]	1 int (2 bytes)	1
	401235	1235	GasAlarm[3]	1 int (2 bytes)	1
	401236	1236	Pressure[0]	1 int (2 bytes)	1
	401237	1237	Pressure[1]	1 int (2 bytes)	1
	401238	1238	Pressure[2]	1 int (2 bytes)	1
	401239	1239	Pressure[3]	1 int (2 bytes)	1
	401240	1240	AlarmRepeatDelay	1 int (2 bytes)	1
	401241	1241	LogicType	1 int (2 bytes)	1
	401242	1242	Language	1 int (2 bytes)	1
	401243	1243	GasType[0]	1 int (2 bytes)	1
	401244	1244	GasType[1]	1 int (2 bytes)	1
	401245	1245	GasType[2]	1 int (2 bytes)	1
	401246	1246	GasType[3]	1 int (2 bytes)	1
	401247	1247	Units[0]	1 int (2 bytes)	1
	401248	1248	Units[1]	1 int (2 bytes)	1
	401249	1249	Units[2]	1 int (2 bytes)	1
	401250	1250	Units[3]	1 int (2 bytes)	1
	401251	1251	HiLimit[0]	1 int (2 bytes)	1

401252	1252	HiLimit[1]	1 int (2 bytes)	1
401253	1253	HiLimit[2]	1 int (2 bytes)	1
401254	1254	HiLimit[3]	1 int (2 bytes)	1
401255	1255	LoLimit[0]	1 int (2 bytes)	1
401256	1256	LoLimit[1]	1 int (2 bytes)	1
401257	1257	LoLimit[2]	1 int (2 bytes)	1
401258	1258	LoLimit[3]	1 int (2 bytes)	1
401259	1259	PressureOffset[0]	1 int (2 bytes)	1
401260	1260	PressureOffset[1]	1 int (2 bytes)	1
401261	1261	PressureOffset[2]	1 int (2 bytes)	1
401262	1262	PressureOffset[3]	1 int (2 bytes)	1
401263	1263	DisplayedText[0] ints (72 chars + 1 int)		37
401300	1300	DisplayedText[1] ints (72 chars + 1 int)		37
401337	1337	DisplayedText[2] ints (72 chars + 1 int)		37
401374	1374	DisplayedText[3] ints (72 chars + 1 int)		37
401411	1411	DisplayedText[4] ints (72 chars + 1 int)		37
401448	1448	DisplayedText[5] ints (72 chars + 1 int)		37
401485	1485	DisplayedText[6] ints (72 chars + 1 int)		37
401522	1522	DisplayedText[7] ints (72 chars + 1 int)		37

ID 4	401839	1839	CommFail	1 int (2 bytes)	1
	401840	1840	SetupChanged	1 int (2 bytes)	1
	401841	1841	BoardType	1 int (2 bytes)	1
	401842	1842	Horn	1 int (2 bytes)	1
	401843	1843	ETextState	1 int (2 bytes)	1
	401844	1844	MasterAlarm	1 int (2 bytes)	1
	401845	1845	GasAlarm[0]	1 int (2 bytes)	1
	401846	1846	GasAlarm[1]	1 int (2 bytes)	1
	401847	1847	GasAlarm[2]	1 int (2 bytes)	1
	401848	1848	GasAlarm[3]	1 int (2 bytes)	1
	401849	1849	Pressure[0]	1 int (2 bytes)	1
	401850	1850	Pressure[1]	1 int (2 bytes)	1
	401851	1851	Pressure[2]	1 int (2 bytes)	1
	401852	1852	Pressure[3]	1 int (2 bytes)	1
	401853	1853	AlarmRepeatDelay	1 int (2 bytes)	1
	401854	1854	LogicType	1 int (2 bytes)	1
	401855	1855	Language	1 int (2 bytes)	1
	401856	1856	GasType[0]	1 int (2 bytes)	1
	401857	1857	GasType[1]	1 int (2 bytes)	1
	401858	1858	GasType[2]	1 int (2 bytes)	1

401859	1859	GasType[3]	1 int (2 bytes)	1
401860	1860	Units[0]	1 int (2 bytes)	1
401861	1861	Units[1]	1 int (2 bytes)	1
401862	1862	Units[2]	1 int (2 bytes)	1
401863	1863	Units[3]	1 int (2 bytes)	1
401864	1864	HiLimit[0]	1 int (2 bytes)	1
401865	1865	HiLimit[1]	1 int (2 bytes)	1
401866	1866	HiLimit[2]	1 int (2 bytes)	1
401867	1867	HiLimit[3]	1 int (2 bytes)	1
401868	1868	LoLimit[0]	1 int (2 bytes)	1
401869	1869	LoLimit[1]	1 int (2 bytes)	1
401870	1870	LoLimit[2]	1 int (2 bytes)	1
401871	1871	LoLimit[3]	1 int (2 bytes)	1
401872	1872	PressureOffset[0]	1 int (2 bytes)	1
401873	1873	PressureOffset[1]	1 int (2 bytes)	1
401874	1874	PressureOffset[2]	1 int (2 bytes)	1
401875	1875	PressureOffset[3]	1 int (2 bytes)	1
401876	1876	DisplayedText[0]	ints (72 chars + 1 int)	37
401913	1913	DisplayedText[1]	ints (72 chars + 1 int)	37
401950	1950	DisplayedText[2]	ints (72 chars + 1 int)	37
401987	1987	DisplayedText[3]	ints (72 chars + 1 int)	37
402024	2024	DisplayedText[4]	ints (72 chars + 1 int)	37
402061	2061	DisplayedText[5]	ints (72 chars + 1 int)	37
402098	2098	DisplayedText[6]	ints (72 chars + 1 int)	37
402135	2135	DisplayedText[7]	ints (72 chars + 1 int)	37

ID 5	402452	2452	CommFail	1 int (2 bytes)	1
	402453	2453	SetupChanged	1 int (2 bytes)	1
	402454	2454	BoardType	1 int (2 bytes)	1
	402455	2455	Horn	1 int (2 bytes)	1
	402456	2456	ETextState	1 int (2 bytes)	1
	402457	2457	MasterAlarm	1 int (2 bytes)	1
	402458	2458	GasAlarm[0]	1 int (2 bytes)	1
	402459	2459	GasAlarm[1]	1 int (2 bytes)	1
	402460	2460	GasAlarm[2]	1 int (2 bytes)	1
	402461	2461	GasAlarm[3]	1 int (2 bytes)	1
	402462	2462	Pressure[0]	1 int (2 bytes)	1
	402463	2463	Pressure[1]	1 int (2 bytes)	1
	402464	2464	Pressure[2]	1 int (2 bytes)	1
	402465	2465	Pressure[3]	1 int (2 bytes)	1

402466	2466	AlarmRepeatDelay	1 int (2 bytes)	1	
402467	2467	LogicType	1 int (2 bytes)	1	
402468	2468	Language	1 int (2 bytes)	1	
402469	2469	GasType[0]	1 int (2 bytes)	1	
402470	2470	GasType[1]	1 int (2 bytes)	1	
402471	2471	GasType[2]	1 int (2 bytes)	1	
402472	2472	GasType[3]	1 int (2 bytes)	1	
402473	2473	Units[0]	1 int (2 bytes)	1	
402474	2474	Units[1]	1 int (2 bytes)	1	
402475	2475	Units[2]	1 int (2 bytes)	1	
402476	2476	Units[3]	1 int (2 bytes)	1	
402477	2477	HiLimit[0]	1 int (2 bytes)	1	
402478	2478	HiLimit[1]	1 int (2 bytes)	1	
402479	2479	HiLimit[2]	1 int (2 bytes)	1	
402480	2480	HiLimit[3]	1 int (2 bytes)	1	
402481	2481	LoLimit[0]	1 int (2 bytes)	1	
402482	2482	LoLimit[1]	1 int (2 bytes)	1	
402483	2483	LoLimit[2]	1 int (2 bytes)	1	
402484	2484	LoLimit[3]	1 int (2 bytes)	1	
402485	2485	PressureOffset[0]	1 int (2 bytes)	1	
402486	2486	PressureOffset[1]	1 int (2 bytes)	1	
402487	2487	PressureOffset[2]	1 int (2 bytes)	1	
402488	2488	PressureOffset[3]	1 int (2 bytes)	1	
402489	2489	DisplayedText[0]	ints (72 chars + 1 int)	37	
402526	2526	DisplayedText[1]	ints (72 chars + 1 int)	37	
402563	2563	DisplayedText[2]	ints (72 chars + 1 int)	37	
402600	2600	DisplayedText[3]	ints (72 chars + 1 int)	37	
402637	2637	DisplayedText[4]	ints (72 chars + 1 int)	37	
402674	2674	DisplayedText[5]	ints (72 chars + 1 int)	37	
402711	2711	DisplayedText[6]	ints (72 chars + 1 int)	37	
402748	2748	DisplayedText[7]	ints (72 chars + 1 int)	37	
ID 6	403065	3065	CommFail	1 int (2 bytes)	1
	403066	3066	SetupChanged	1 int (2 bytes)	1
	403067	3067	BoardType	1 int (2 bytes)	1
	403068	3068	Horn	1 int (2 bytes)	1
	403069	3069	ETextState	1 int (2 bytes)	1
	403070	3070	MasterAlarm	1 int (2 bytes)	1
	403071	3071	GasAlarm[0]	1 int (2 bytes)	1
	403072	3072	GasAlarm[1]	1 int (2 bytes)	1

403073	3073	GasAlarm[2]	1 int (2 bytes)	1	
403074	3074	GasAlarm[3]	1 int (2 bytes)	1	
403075	3075	Pressure[0]	1 int (2 bytes)	1	
403076	3076	Pressure[1]	1 int (2 bytes)	1	
403077	3077	Pressure[2]	1 int (2 bytes)	1	
403078	3078	Pressure[3]	1 int (2 bytes)	1	
403079	3079	AlarmRepeatDelay	1 int (2 bytes)	1	
403080	3080	LogicType	1 int (2 bytes)	1	
403081	3081	Language	1 int (2 bytes)	1	
403082	3082	GasType[0]	1 int (2 bytes)	1	
403083	3083	GasType[1]	1 int (2 bytes)	1	
403084	3084	GasType[2]	1 int (2 bytes)	1	
403085	3085	GasType[3]	1 int (2 bytes)	1	
403086	3086	Units[0]	1 int (2 bytes)	1	
403087	3087	Units[1]	1 int (2 bytes)	1	
403088	3088	Units[2]	1 int (2 bytes)	1	
403089	3089	Units[3]	1 int (2 bytes)	1	
403090	3090	HiLimit[0]	1 int (2 bytes)	1	
403091	3091	HiLimit[1]	1 int (2 bytes)	1	
403092	3092	HiLimit[2]	1 int (2 bytes)	1	
403093	3093	HiLimit[3]	1 int (2 bytes)	1	
403094	3094	LoLimit[0]	1 int (2 bytes)	1	
403095	3095	LoLimit[1]	1 int (2 bytes)	1	
403096	3096	LoLimit[2]	1 int (2 bytes)	1	
403097	3097	LoLimit[3]	1 int (2 bytes)	1	
403098	3098	PressureOffset[0]	1 int (2 bytes)	1	
403099	3099	PressureOffset[1]	1 int (2 bytes)	1	
403100	3100	PressureOffset[2]	1 int (2 bytes)	1	
403101	3101	PressureOffset[3]	1 int (2 bytes)	1	
403102	3102	DisplayedText[0] ints (72 chars + 1 int)		37	
403139	3139	DisplayedText[1] ints (72 chars + 1 int)		37	
403176	3176	DisplayedText[2] ints (72 chars + 1 int)		37	
403213	3213	DisplayedText[3] ints (72 chars + 1 int)		37	
403250	3250	DisplayedText[4] ints (72 chars + 1 int)		37	
403287	3287	DisplayedText[5] ints (72 chars + 1 int)		37	
403324	3324	DisplayedText[6] ints (72 chars + 1 int)		37	
403361	3361	DisplayedText[7] ints (72 chars + 1 int)		37	
ID 7	403678	3678	CommFail	1 int (2 bytes)	1
	403679	3679	SetupChanged	1 int (2 bytes)	1

403680	3680	BoardType	1 int (2 bytes)	1
403681	3681	Horn	1 int (2 bytes)	1
403682	3682	ETextState	1 int (2 bytes)	1
403683	3683	MasterAlarm	1 int (2 bytes)	1
403684	3684	GasAlarm[0]	1 int (2 bytes)	1
403685	3685	GasAlarm[1]	1 int (2 bytes)	1
403686	3686	GasAlarm[2]	1 int (2 bytes)	1
403687	3687	GasAlarm[3]	1 int (2 bytes)	1
403688	3688	Pressure[0]	1 int (2 bytes)	1
403689	3689	Pressure[1]	1 int (2 bytes)	1
403690	3690	Pressure[2]	1 int (2 bytes)	1
403691	3691	Pressure[3]	1 int (2 bytes)	1
403692	3692	AlarmRepeatDelay	1 int (2 bytes)	1
403693	3693	LogicType	1 int (2 bytes)	1
403694	3694	Language	1 int (2 bytes)	1
403695	3695	GasType[0]	1 int (2 bytes)	1
403696	3696	GasType[1]	1 int (2 bytes)	1
403697	3697	GasType[2]	1 int (2 bytes)	1
403698	3698	GasType[3]	1 int (2 bytes)	1
403699	3699	Units[0]	1 int (2 bytes)	1
403700	3700	Units[1]	1 int (2 bytes)	1
403701	3701	Units[2]	1 int (2 bytes)	1
403702	3702	Units[3]	1 int (2 bytes)	1
403703	3703	HiLimit[0]	1 int (2 bytes)	1
403704	3704	HiLimit[1]	1 int (2 bytes)	1
403705	3705	HiLimit[2]	1 int (2 bytes)	1
403706	3706	HiLimit[3]	1 int (2 bytes)	1
403707	3707	LoLimit[0]	1 int (2 bytes)	1
403708	3708	LoLimit[1]	1 int (2 bytes)	1
403709	3709	LoLimit[2]	1 int (2 bytes)	1
403710	3710	LoLimit[3]	1 int (2 bytes)	1
403711	3711	PressureOffset[0]	1 int (2 bytes)	1
403712	3712	PressureOffset[1]	1 int (2 bytes)	1
403713	3713	PressureOffset[2]	1 int (2 bytes)	1
403714	3714	PressureOffset[3]	1 int (2 bytes)	1
403715	3715	DisplayedText[0]	ints (72 chars + 1 int)	37
403752	3752	DisplayedText[1]	ints (72 chars + 1 int)	37
403789	3789	DisplayedText[2]	ints (72 chars + 1 int)	37
403826	3826	DisplayedText[3]	ints (72 chars + 1 int)	37
403863	3863	DisplayedText[4]	ints (72 chars + 1 int)	37

403900	3900	DisplayedText[5] ints (72 chars + 1 int)	37
403937	3937	DisplayedText[6] ints (72 chars + 1 int)	37
403974	3974	DisplayedText[7] ints (72 chars + 1 int)	37

ID 8	404291	4291	CommFail	1 int (2 bytes)	1
	404292	4292	SetupChanged	1 int (2 bytes)	1
	404293	4293	BoardType	1 int (2 bytes)	1
	404294	4294	Horn	1 int (2 bytes)	1
	404295	4295	ETextState	1 int (2 bytes)	1
	404296	4296	MasterAlarm	1 int (2 bytes)	1
	404297	4297	GasAlarm[0]	1 int (2 bytes)	1
	404298	4298	GasAlarm[1]	1 int (2 bytes)	1
	404299	4299	GasAlarm[2]	1 int (2 bytes)	1
	404300	4300	GasAlarm[3]	1 int (2 bytes)	1
	404301	4301	Pressure[0]	1 int (2 bytes)	1
	404302	4302	Pressure[1]	1 int (2 bytes)	1
	404303	4303	Pressure[2]	1 int (2 bytes)	1
	404304	4304	Pressure[3]	1 int (2 bytes)	1
	404305	4305	AlarmRepeatDelay	1 int (2 bytes)	1
	404306	4306	LogicType	1 int (2 bytes)	1
	404307	4307	Language	1 int (2 bytes)	1
	404308	4308	GasType[0]	1 int (2 bytes)	1
	404309	4309	GasType[1]	1 int (2 bytes)	1
	404310	4310	GasType[2]	1 int (2 bytes)	1
	404311	4311	GasType[3]	1 int (2 bytes)	1
	404312	4312	Units[0]	1 int (2 bytes)	1
	404313	4313	Units[1]	1 int (2 bytes)	1
	404314	4314	Units[2]	1 int (2 bytes)	1
	404315	4315	Units[3]	1 int (2 bytes)	1
	404316	4316	HiLimit[0]	1 int (2 bytes)	1
	404317	4317	HiLimit[1]	1 int (2 bytes)	1
	404318	4318	HiLimit[2]	1 int (2 bytes)	1
	404319	4319	HiLimit[3]	1 int (2 bytes)	1
	404320	4320	LoLimit[0]	1 int (2 bytes)	1
	404321	4321	LoLimit[1]	1 int (2 bytes)	1
	404322	4322	LoLimit[2]	1 int (2 bytes)	1
	404323	4323	LoLimit[3]	1 int (2 bytes)	1
	404324	4324	PressureOffset[0]	1 int (2 bytes)	1
	404325	4325	PressureOffset[1]	1 int (2 bytes)	1
	404326	4326	PressureOffset[2]	1 int (2 bytes)	1

404327	4327	PressureOffset[3]	1 int (2 bytes)	1
404328	4328	DisplayedText[0]	ints (72 chars + 1 int)	37
404365	4365	DisplayedText[1]	ints (72 chars + 1 int)	37
404402	4402	DisplayedText[2]	ints (72 chars + 1 int)	37
404439	4439	DisplayedText[3]	ints (72 chars + 1 int)	37
404476	4476	DisplayedText[4]	ints (72 chars + 1 int)	37
404513	4513	DisplayedText[5]	ints (72 chars + 1 int)	37
404550	4550	DisplayedText[6]	ints (72 chars + 1 int)	37
404587	4587	DisplayedText[7]	ints (72 chars + 1 int)	37

ID 9

404904	4904	CommFail	1 int (2 bytes)	1
404905	4905	SetupChanged	1 int (2 bytes)	1
404906	4906	BoardType	1 int (2 bytes)	1
404907	4907	Horn	1 int (2 bytes)	1
404908	4908	ETextState	1 int (2 bytes)	1
404909	4909	MasterAlarm	1 int (2 bytes)	1
404910	4910	GasAlarm[0]	1 int (2 bytes)	1
404911	4911	GasAlarm[1]	1 int (2 bytes)	1
404912	4912	GasAlarm[2]	1 int (2 bytes)	1
404913	4913	GasAlarm[3]	1 int (2 bytes)	1
404914	4914	Pressure[0]	1 int (2 bytes)	1
404915	4915	Pressure[1]	1 int (2 bytes)	1
404916	4916	Pressure[2]	1 int (2 bytes)	1
404917	4917	Pressure[3]	1 int (2 bytes)	1
404918	4918	AlarmRepeatDelay	1 int (2 bytes)	1
404919	4919	LogicType	1 int (2 bytes)	1
404920	4920	Language	1 int (2 bytes)	1
404921	4921	GasType[0]	1 int (2 bytes)	1
404922	4922	GasType[1]	1 int (2 bytes)	1
404923	4923	GasType[2]	1 int (2 bytes)	1
404924	4924	GasType[3]	1 int (2 bytes)	1
404925	4925	Units[0]	1 int (2 bytes)	1
404926	4926	Units[1]	1 int (2 bytes)	1
404927	4927	Units[2]	1 int (2 bytes)	1
404928	4928	Units[3]	1 int (2 bytes)	1
404929	4929	HiLimit[0]	1 int (2 bytes)	1
404930	4930	HiLimit[1]	1 int (2 bytes)	1
404931	4931	HiLimit[2]	1 int (2 bytes)	1
404932	4932	HiLimit[3]	1 int (2 bytes)	1
404933	4933	LoLimit[0]	1 int (2 bytes)	1

404934	4934	LoLimit[1]	1 int (2 bytes)	1
404935	4935	LoLimit[2]	1 int (2 bytes)	1
404936	4936	LoLimit[3]	1 int (2 bytes)	1
404937	4937	PressureOffset[0]	1 int (2 bytes)	1
404938	4938	PressureOffset[1]	1 int (2 bytes)	1
404939	4939	PressureOffset[2]	1 int (2 bytes)	1
404940	4940	PressureOffset[3]	1 int (2 bytes)	1
404941	4941	DisplayedText[0] ints (72 chars + 1 int)		37
404978	4978	DisplayedText[1] ints (72 chars + 1 int)		37
405015	5015	DisplayedText[2] ints (72 chars + 1 int)		37
405052	5052	DisplayedText[3] ints (72 chars + 1 int)		37
405089	5089	DisplayedText[4] ints (72 chars + 1 int)		37
405126	5126	DisplayedText[5] ints (72 chars + 1 int)		37
405163	5163	DisplayedText[6] ints (72 chars + 1 int)		37
405200	5200	DisplayedText[7] ints (72 chars + 1 int)		37

ID 10	405517	5517	CommFail	1 int (2 bytes)	1
	405518	5518	SetupChanged	1 int (2 bytes)	1
	405519	5519	BoardType	1 int (2 bytes)	1
	405520	5520	Horn	1 int (2 bytes)	1
	405521	5521	ETextState	1 int (2 bytes)	1
	405522	5522	MasterAlarm	1 int (2 bytes)	1
	405523	5523	GasAlarm[0]	1 int (2 bytes)	1
	405524	5524	GasAlarm[1]	1 int (2 bytes)	1
	405525	5525	GasAlarm[2]	1 int (2 bytes)	1
	405526	5526	GasAlarm[3]	1 int (2 bytes)	1
	405527	5527	Pressure[0]	1 int (2 bytes)	1
	405528	5528	Pressure[1]	1 int (2 bytes)	1
	405529	5529	Pressure[2]	1 int (2 bytes)	1
	405530	5530	Pressure[3]	1 int (2 bytes)	1
	405531	5531	AlarmRepeatDelay	1 int (2 bytes)	1
	405532	5532	LogicType	1 int (2 bytes)	1
	405533	5533	Language	1 int (2 bytes)	1
	405534	5534	GasType[0]	1 int (2 bytes)	1
	405535	5535	GasType[1]	1 int (2 bytes)	1
	405536	5536	GasType[2]	1 int (2 bytes)	1
	405537	5537	GasType[3]	1 int (2 bytes)	1
	405538	5538	Units[0]	1 int (2 bytes)	1
	405539	5539	Units[1]	1 int (2 bytes)	1
	405540	5540	Units[2]	1 int (2 bytes)	1

405541	5541	Units[3]	1 int (2 bytes)	1
405542	5542	HiLimit[0]	1 int (2 bytes)	1
405543	5543	HiLimit[1]	1 int (2 bytes)	1
405544	5544	HiLimit[2]	1 int (2 bytes)	1
405545	5545	HiLimit[3]	1 int (2 bytes)	1
405546	5546	LoLimit[0]	1 int (2 bytes)	1
405547	5547	LoLimit[1]	1 int (2 bytes)	1
405548	5548	LoLimit[2]	1 int (2 bytes)	1
405549	5549	LoLimit[3]	1 int (2 bytes)	1
405550	5550	PressureOffset[0]	1 int (2 bytes)	1
405551	5551	PressureOffset[1]	1 int (2 bytes)	1
405552	5552	PressureOffset[2]	1 int (2 bytes)	1
405553	5553	PressureOffset[3]	1 int (2 bytes)	1
405554	5554	DisplayedText[0]	ints (72 chars + 1 int)	37
405591	5591	DisplayedText[1]	ints (72 chars + 1 int)	37
405628	5628	DisplayedText[2]	ints (72 chars + 1 int)	37
405665	5665	DisplayedText[3]	ints (72 chars + 1 int)	37
405702	5702	DisplayedText[4]	ints (72 chars + 1 int)	37
405739	5739	DisplayedText[5]	ints (72 chars + 1 int)	37
405776	5776	DisplayedText[6]	ints (72 chars + 1 int)	37
405813	5813	DisplayedText[7]	ints (72 chars + 1 int)	37

ID 11	406130	6130	CommFail	1 int (2 bytes)	1
	406131	6131	SetupChanged	1 int (2 bytes)	1
	406132	6132	BoardType	1 int (2 bytes)	1
	406133	6133	Horn	1 int (2 bytes)	1
	406134	6134	ETextState	1 int (2 bytes)	1
	406135	6135	MasterAlarm	1 int (2 bytes)	1
	406136	6136	GasAlarm[0]	1 int (2 bytes)	1
	406137	6137	GasAlarm[1]	1 int (2 bytes)	1
	406138	6138	GasAlarm[2]	1 int (2 bytes)	1
	406139	6139	GasAlarm[3]	1 int (2 bytes)	1
	406140	6140	Pressure[0]	1 int (2 bytes)	1
	406141	6141	Pressure[1]	1 int (2 bytes)	1
	406142	6142	Pressure[2]	1 int (2 bytes)	1
	406143	6143	Pressure[3]	1 int (2 bytes)	1
	406144	6144	AlarmRepeatDelay	1 int (2 bytes)	1
	406145	6145	LogicType	1 int (2 bytes)	1
	406146	6146	Language	1 int (2 bytes)	1
	406147	6147	GasType[0]	1 int (2 bytes)	1

406148	6148	GasType[1]	1 int (2 bytes)	1
406149	6149	GasType[2]	1 int (2 bytes)	1
406150	6150	GasType[3]	1 int (2 bytes)	1
406151	6151	Units[0]	1 int (2 bytes)	1
406152	6152	Units[1]	1 int (2 bytes)	1
406153	6153	Units[2]	1 int (2 bytes)	1
406154	6154	Units[3]	1 int (2 bytes)	1
406155	6155	HiLimit[0]	1 int (2 bytes)	1
406156	6156	HiLimit[1]	1 int (2 bytes)	1
406157	6157	HiLimit[2]	1 int (2 bytes)	1
406158	6158	HiLimit[3]	1 int (2 bytes)	1
406159	6159	LoLimit[0]	1 int (2 bytes)	1
406160	6160	LoLimit[1]	1 int (2 bytes)	1
406161	6161	LoLimit[2]	1 int (2 bytes)	1
406162	6162	LoLimit[3]	1 int (2 bytes)	1
406163	6163	PressureOffset[0]	1 int (2 bytes)	1
406164	6164	PressureOffset[1]	1 int (2 bytes)	1
406165	6165	PressureOffset[2]	1 int (2 bytes)	1
406166	6166	PressureOffset[3]	1 int (2 bytes)	1
406167	6167	DisplayedText[0] ints (72 chars + 1 int)		37
406204	6204	DisplayedText[1] ints (72 chars + 1 int)		37
406241	6241	DisplayedText[2] ints (72 chars + 1 int)		37
406278	6278	DisplayedText[3] ints (72 chars + 1 int)		37
406315	6315	DisplayedText[4] ints (72 chars + 1 int)		37
406352	6352	DisplayedText[5] ints (72 chars + 1 int)		37
406389	6389	DisplayedText[6] ints (72 chars + 1 int)		37
406426	6426	DisplayedText[7] ints (72 chars + 1 int)		37

ID 12	406743	6743	CommFail	1 int (2 bytes)	1
	406744	6744	SetupChanged	1 int (2 bytes)	1
	406745	6745	BoardType	1 int (2 bytes)	1
	406746	6746	Horn	1 int (2 bytes)	1
	406747	6747	ETextState	1 int (2 bytes)	1
	406748	6748	MasterAlarm	1 int (2 bytes)	1
	406749	6749	GasAlarm[0]	1 int (2 bytes)	1
	406750	6750	GasAlarm[1]	1 int (2 bytes)	1
	406751	6751	GasAlarm[2]	1 int (2 bytes)	1
	406752	6752	GasAlarm[3]	1 int (2 bytes)	1
	406753	6753	Pressure[0]	1 int (2 bytes)	1
	406754	6754	Pressure[1]	1 int (2 bytes)	1

406755	6755	Pressure[2]	1 int (2 bytes)	1	
406756	6756	Pressure[3]	1 int (2 bytes)	1	
406757	6757	AlarmRepeatDelay	1 int (2 bytes)	1	
406758	6758	LogicType	1 int (2 bytes)	1	
406759	6759	Language	1 int (2 bytes)	1	
406760	6760	GasType[0]	1 int (2 bytes)	1	
406761	6761	GasType[1]	1 int (2 bytes)	1	
406762	6762	GasType[2]	1 int (2 bytes)	1	
406763	6763	GasType[3]	1 int (2 bytes)	1	
406764	6764	Units[0]	1 int (2 bytes)	1	
406765	6765	Units[1]	1 int (2 bytes)	1	
406766	6766	Units[2]	1 int (2 bytes)	1	
406767	6767	Units[3]	1 int (2 bytes)	1	
406768	6768	HiLimit[0]	1 int (2 bytes)	1	
406769	6769	HiLimit[1]	1 int (2 bytes)	1	
406770	6770	HiLimit[2]	1 int (2 bytes)	1	
406771	6771	HiLimit[3]	1 int (2 bytes)	1	
406772	6772	LoLimit[0]	1 int (2 bytes)	1	
406773	6773	LoLimit[1]	1 int (2 bytes)	1	
406774	6774	LoLimit[2]	1 int (2 bytes)	1	
406775	6775	LoLimit[3]	1 int (2 bytes)	1	
406776	6776	PressureOffset[0]	1 int (2 bytes)	1	
406777	6777	PressureOffset[1]	1 int (2 bytes)	1	
406778	6778	PressureOffset[2]	1 int (2 bytes)	1	
406779	6779	PressureOffset[3]	1 int (2 bytes)	1	
406780	6780	DisplayedText[0] ints (72 chars + 1 int)		37	
406817	6817	DisplayedText[1] ints (72 chars + 1 int)		37	
406854	6854	DisplayedText[2] ints (72 chars + 1 int)		37	
406891	6891	DisplayedText[3] ints (72 chars + 1 int)		37	
406928	6928	DisplayedText[4] ints (72 chars + 1 int)		37	
406965	6965	DisplayedText[5] ints (72 chars + 1 int)		37	
407002	7002	DisplayedText[6] ints (72 chars + 1 int)		37	
407039	7039	DisplayedText[7] ints (72 chars + 1 int)		37	
ID 13	407356	7356	CommFail	1 int (2 bytes)	1
	407357	7357	SetupChanged	1 int (2 bytes)	1
	407358	7358	BoardType	1 int (2 bytes)	1
	407359	7359	Horn	1 int (2 bytes)	1
	407360	7360	ETextState	1 int (2 bytes)	1
	407361	7361	MasterAlarm	1 int (2 bytes)	1

407362	7362	GasAlarm[0]	1 int (2 bytes)	1
407363	7363	GasAlarm[1]	1 int (2 bytes)	1
407364	7364	GasAlarm[2]	1 int (2 bytes)	1
407365	7365	GasAlarm[3]	1 int (2 bytes)	1
407366	7366	Pressure[0]	1 int (2 bytes)	1
407367	7367	Pressure[1]	1 int (2 bytes)	1
407368	7368	Pressure[2]	1 int (2 bytes)	1
407369	7369	Pressure[3]	1 int (2 bytes)	1
407370	7370	AlarmRepeatDelay	1 int (2 bytes)	1
407371	7371	LogicType	1 int (2 bytes)	1
407372	7372	Language	1 int (2 bytes)	1
407373	7373	GasType[0]	1 int (2 bytes)	1
407374	7374	GasType[1]	1 int (2 bytes)	1
407375	7375	GasType[2]	1 int (2 bytes)	1
407376	7376	GasType[3]	1 int (2 bytes)	1
407377	7377	Units[0]	1 int (2 bytes)	1
407378	7378	Units[1]	1 int (2 bytes)	1
407379	7379	Units[2]	1 int (2 bytes)	1
407380	7380	Units[3]	1 int (2 bytes)	1
407381	7381	HiLimit[0]	1 int (2 bytes)	1
407382	7382	HiLimit[1]	1 int (2 bytes)	1
407383	7383	HiLimit[2]	1 int (2 bytes)	1
407384	7384	HiLimit[3]	1 int (2 bytes)	1
407385	7385	LoLimit[0]	1 int (2 bytes)	1
407386	7386	LoLimit[1]	1 int (2 bytes)	1
407387	7387	LoLimit[2]	1 int (2 bytes)	1
407388	7388	LoLimit[3]	1 int (2 bytes)	1
407389	7389	PressureOffset[0]	1 int (2 bytes)	1
407390	7390	PressureOffset[1]	1 int (2 bytes)	1
407391	7391	PressureOffset[2]	1 int (2 bytes)	1
407392	7392	PressureOffset[3]	1 int (2 bytes)	1
407393	7393	DisplayedText[0]	ints (72 chars + 1 int)	37
407430	7430	DisplayedText[1]	ints (72 chars + 1 int)	37
407467	7467	DisplayedText[2]	ints (72 chars + 1 int)	37
407504	7504	DisplayedText[3]	ints (72 chars + 1 int)	37
407541	7541	DisplayedText[4]	ints (72 chars + 1 int)	37
407578	7578	DisplayedText[5]	ints (72 chars + 1 int)	37
407615	7615	DisplayedText[6]	ints (72 chars + 1 int)	37
407652	7652	DisplayedText[7]	ints (72 chars + 1 int)	37

ID 14	407969	7969	CommFail	1 int (2 bytes)	1
	407970	7970	SetupChanged	1 int (2 bytes)	1
	407971	7971	BoardType	1 int (2 bytes)	1
	407972	7972	Horn	1 int (2 bytes)	1
	407973	7973	ETextState	1 int (2 bytes)	1
	407974	7974	MasterAlarm	1 int (2 bytes)	1
	407975	7975	GasAlarm[0]	1 int (2 bytes)	1
	407976	7976	GasAlarm[1]	1 int (2 bytes)	1
	407977	7977	GasAlarm[2]	1 int (2 bytes)	1
	407978	7978	GasAlarm[3]	1 int (2 bytes)	1
	407979	7979	Pressure[0]	1 int (2 bytes)	1
	407980	7980	Pressure[1]	1 int (2 bytes)	1
	407981	7981	Pressure[2]	1 int (2 bytes)	1
	407982	7982	Pressure[3]	1 int (2 bytes)	1
	407983	7983	AlarmRepeatDelay	1 int (2 bytes)	1
	407984	7984	LogicType	1 int (2 bytes)	1
	407985	7985	Language	1 int (2 bytes)	1
	407986	7986	GasType[0]	1 int (2 bytes)	1
	407987	7987	GasType[1]	1 int (2 bytes)	1
	407988	7988	GasType[2]	1 int (2 bytes)	1
	407989	7989	GasType[3]	1 int (2 bytes)	1
	407990	7990	Units[0]	1 int (2 bytes)	1
	407991	7991	Units[1]	1 int (2 bytes)	1
	407992	7992	Units[2]	1 int (2 bytes)	1
	407993	7993	Units[3]	1 int (2 bytes)	1
	407994	7994	HiLimit[0]	1 int (2 bytes)	1
	407995	7995	HiLimit[1]	1 int (2 bytes)	1
	407996	7996	HiLimit[2]	1 int (2 bytes)	1
	407997	7997	HiLimit[3]	1 int (2 bytes)	1
	407998	7998	LoLimit[0]	1 int (2 bytes)	1
	407999	7999	LoLimit[1]	1 int (2 bytes)	1
	408000	8000	LoLimit[2]	1 int (2 bytes)	1
	408001	8001	LoLimit[3]	1 int (2 bytes)	1
	408002	8002	PressureOffset[0]	1 int (2 bytes)	1
	408003	8003	PressureOffset[1]	1 int (2 bytes)	1
	408004	8004	PressureOffset[2]	1 int (2 bytes)	1
	408005	8005	PressureOffset[3]	1 int (2 bytes)	1
	408006	8006	DisplayedText[0]	ints (72 chars + 1 int)	37
	408043	8043	DisplayedText[1]	ints (72 chars + 1 int)	37
	408080	8080	DisplayedText[2]	ints (72 chars + 1 int)	37

408117	8117	DisplayedText[3] ints (72 chars + 1 int)	37
408154	8154	DisplayedText[4] ints (72 chars + 1 int)	37
408191	8191	DisplayedText[5] ints (72 chars + 1 int)	37
408228	8228	DisplayedText[6] ints (72 chars + 1 int)	37
408265	8265	DisplayedText[7] ints (72 chars + 1 int)	37

ID 15	408582	8582	CommFail	1 int (2 bytes)	1
	408583	8583	SetupChanged	1 int (2 bytes)	1
	408584	8584	BoardType	1 int (2 bytes)	1
	408585	8585	Horn	1 int (2 bytes)	1
	408586	8586	ETextState	1 int (2 bytes)	1
	408587	8587	MasterAlarm	1 int (2 bytes)	1
	408588	8588	GasAlarm[0]	1 int (2 bytes)	1
	408589	8589	GasAlarm[1]	1 int (2 bytes)	1
	408590	8590	GasAlarm[2]	1 int (2 bytes)	1
	408591	8591	GasAlarm[3]	1 int (2 bytes)	1
	408592	8592	Pressure[0]	1 int (2 bytes)	1
	408593	8593	Pressure[1]	1 int (2 bytes)	1
	408594	8594	Pressure[2]	1 int (2 bytes)	1
	408595	8595	Pressure[3]	1 int (2 bytes)	1
	408596	8596	AlarmRepeatDelay	1 int (2 bytes)	1
	408597	8597	LogicType	1 int (2 bytes)	1
	408598	8598	Language	1 int (2 bytes)	1
	408599	8599	GasType[0]	1 int (2 bytes)	1
	408600	8600	GasType[1]	1 int (2 bytes)	1
	408601	8601	GasType[2]	1 int (2 bytes)	1
	408602	8602	GasType[3]	1 int (2 bytes)	1
	408603	8603	Units[0]	1 int (2 bytes)	1
	408604	8604	Units[1]	1 int (2 bytes)	1
	408605	8605	Units[2]	1 int (2 bytes)	1
	408606	8606	Units[3]	1 int (2 bytes)	1
	408607	8607	HiLimit[0]	1 int (2 bytes)	1
	408608	8608	HiLimit[1]	1 int (2 bytes)	1
	408609	8609	HiLimit[2]	1 int (2 bytes)	1
	408610	8610	HiLimit[3]	1 int (2 bytes)	1
	408611	8611	LoLimit[0]	1 int (2 bytes)	1
	408612	8612	LoLimit[1]	1 int (2 bytes)	1
	408613	8613	LoLimit[2]	1 int (2 bytes)	1
	408614	8614	LoLimit[3]	1 int (2 bytes)	1
	408615	8615	PressureOffset[0]	1 int (2 bytes)	1

408616	8616	PressureOffset[1]	1 int (2 bytes)	1
408617	8617	PressureOffset[2]	1 int (2 bytes)	1
408618	8618	PressureOffset[3]	1 int (2 bytes)	1
408619	8619	DisplayedText[0]	ints (72 chars + 1 int)	37
408656	8656	DisplayedText[1]	ints (72 chars + 1 int)	37
408693	8693	DisplayedText[2]	ints (72 chars + 1 int)	37
408730	8730	DisplayedText[3]	ints (72 chars + 1 int)	37
408767	8767	DisplayedText[4]	ints (72 chars + 1 int)	37
408804	8804	DisplayedText[5]	ints (72 chars + 1 int)	37
408841	8841	DisplayedText[6]	ints (72 chars + 1 int)	37
408878	8878	DisplayedText[7]	ints (72 chars + 1 int)	37

ID 16	409195	9195	CommFail	1 int (2 bytes)	1
	409196	9196	SetupChanged	1 int (2 bytes)	1
	409197	9197	BoardType	1 int (2 bytes)	1
	409198	9198	Horn	1 int (2 bytes)	1
	409199	9199	ETextState	1 int (2 bytes)	1
	409200	9200	MasterAlarm	1 int (2 bytes)	1
	409201	9201	GasAlarm[0]	1 int (2 bytes)	1
	409202	9202	GasAlarm[1]	1 int (2 bytes)	1
	409203	9203	GasAlarm[2]	1 int (2 bytes)	1
	409204	9204	GasAlarm[3]	1 int (2 bytes)	1
	409205	9205	Pressure[0]	1 int (2 bytes)	1
	409206	9206	Pressure[1]	1 int (2 bytes)	1
	409207	9207	Pressure[2]	1 int (2 bytes)	1
	409208	9208	Pressure[3]	1 int (2 bytes)	1
	409209	9209	AlarmRepeatDelay	1 int (2 bytes)	1
	409210	9210	LogicType	1 int (2 bytes)	1
	409211	9211	Language	1 int (2 bytes)	1
	409212	9212	GasType[0]	1 int (2 bytes)	1
	409213	9213	GasType[1]	1 int (2 bytes)	1
	409214	9214	GasType[2]	1 int (2 bytes)	1
	409215	9215	GasType[3]	1 int (2 bytes)	1
	409216	9216	Units[0]	1 int (2 bytes)	1
	409217	9217	Units[1]	1 int (2 bytes)	1
	409218	9218	Units[2]	1 int (2 bytes)	1
	409219	9219	Units[3]	1 int (2 bytes)	1
	409220	9220	HiLimit[0]	1 int (2 bytes)	1
	409221	9221	HiLimit[1]	1 int (2 bytes)	1
	409222	9222	HiLimit[2]	1 int (2 bytes)	1

409223	9223	HiLimit[3]	1 int (2 bytes)	1
409224	9224	LoLimit[0]	1 int (2 bytes)	1
409225	9225	LoLimit[1]	1 int (2 bytes)	1
409226	9226	LoLimit[2]	1 int (2 bytes)	1
409227	9227	LoLimit[3]	1 int (2 bytes)	1
409228	9228	PressureOffset[0]	1 int (2 bytes)	1
409229	9229	PressureOffset[1]	1 int (2 bytes)	1
409230	9230	PressureOffset[2]	1 int (2 bytes)	1
409231	9231	PressureOffset[3]	1 int (2 bytes)	1
409232	9232	DisplayedText[0]	ints (72 chars + 1 int)	37
409269	9269	DisplayedText[1]	ints (72 chars + 1 int)	37
409306	9306	DisplayedText[2]	ints (72 chars + 1 int)	37
409343	9343	DisplayedText[3]	ints (72 chars + 1 int)	37
409380	9380	DisplayedText[4]	ints (72 chars + 1 int)	37
409417	9417	DisplayedText[5]	ints (72 chars + 1 int)	37
409454	9454	DisplayedText[6]	ints (72 chars + 1 int)	37
409491	9491	DisplayedText[7]	ints (72 chars + 1 int)	37